
2. PROJECTION SYSTEMS - C) CHOOSING A MAP PROJECTION


onext

The cartographer's task is to ensure that the right type of projection is used for any particular map. A well chosen map projection takes care that scale distortions remain within certain limits and that map properties match to the purpose of the map. In theory, the selection of a map projection for a particular area can be made on the basis of:

- 1. the **shape** of the area,
- 2. the *location* (and orientation) of the area, and
- 3. the **purpose** of the map.

Ad 1) Ideally, the general **shape** of the mapping area should match with the distortion pattern of a specific projection (see figure below).





Ad 3) Once the class and aspect of the map projection have been selected, the distortion property of the map projection has to be chosen. The most appropriate type of distortion property for a map depends largely on the purpose for which it will be used.

Map projections with a conformal distortion property represent angles and local shapes correctly, but as the region becomes larger, they show considerable area distortions. An example is the Mercator projection. Although Greenland is only one-eighth the size of South America, Greenland appears to be larger on the Mercator projection. Maps used for the measurement of angles (e.g. aeronautical charts, topographic maps) often make use of a conformal map projection.

Map projections with a **equal-area distortion property** on the other hand, represent areas correctly, but as the region becomes larger, it shows considerable distortions of angles and consequently shapes. Maps which are to be used for measuring areas (e.g. distribution maps) often make use of an equal-area map projection.

The equidistant distortion property is achievable only to a limited degree. That is, true distances can be shown only from one or two points to any other point on the map or in certain directions. If a map is true to scale along the meridians (i.e. no distortion in North-South direction) we say that the map is equidistant along the meridians (e.g. the equidistant cylindrical projection in the figure below). If a map is true to scale along all parallels we say the map is equidistant along the parallels (i.e. no distortion in East-West direction). Maps which require correct distances measured from the centre of the map to any point (e.g. air-route, radio or seismic maps) or maps which require reasonable area and angle distortions (several thematic maps) often make use of an equidistant map projection



<u>Home</u> Self study Contents Intro 1.Graticule / topographic grid 2.Projection **Systems** (a/b/c/d)3.<u>Plane</u> rectangular coordinate

<u>systems</u> (a/b)| <u>4.Coordinate</u> transformations

5.Satellitebased positioning (<u>a/b</u>)

In summary, the ideal map projection for any country would either be an azimuthal, cylindrical, or conic projection, depending on the shape of the area, with a secant projection plane located along the main axis of the country or the area of interest. The selected distortion property depends largely on the purpose of the map.

previous - next>

Copyright <u>United Nations Statistics Division</u> and <u>International Cartographic Association</u>, July 2012